



*Full credit is given to the above companies including the OS that this PDF file was generated!*

### ***Rocky Enterprise Linux 9.2 Manual Pages on command 'dd.1'***

**\$ man dd.1**

DD(1) User Commands DD(1)

NAME

dd - convert and copy a file

SYNOPSIS

dd [OPERAND]...

dd OPTION

DESCRIPTION

Copy a file, converting and formatting according to the operands.

bs=BYTES

read and write up to BYTES bytes at a time (default: 512); over?

rides ibs and obs

cbs=BYTES

convert BYTES bytes at a time

conv=CONVS

convert the file as per the comma separated symbol list

count=N

copy only N input blocks

ibs=BYTES

read up to BYTES bytes at a time (default: 512)

if=FILE

read from FILE instead of stdin

iflag=FLAGS

read as per the comma separated symbol list

obs=BYTES

write BYTES bytes at a time (default: 512)

of=FILE

write to FILE instead of stdout

oflag=FLAGS

write as per the comma separated symbol list

seek=N skip N obs-sized blocks at start of output

skip=N skip N obs-sized blocks at start of input

status=LEVEL

The LEVEL of information to print to stderr; 'none' suppresses everything but error messages, 'noxfers' suppresses the final transfer statistics, 'progress' shows periodic transfer statistics

N and BYTES may be followed by the following multiplicative suffixes:

c=1, w=2, b=512, kB=1000, K=1024, MB=1000\*1000, M=1024\*1024, xM=M,

GB=1000\*1000\*1000, G=1024\*1024\*1024, and so on for T, P, E, Z, Y. Binary

prefixes can be used, too: KiB=K, MiB=M, and so on.

Each CONV symbol may be:

ascii from EBCDIC to ASCII

ebcdic from ASCII to EBCDIC

ibm from ASCII to alternate EBCDIC

block pad newline-terminated records with spaces to cbs-size

unblock

replace trailing spaces in cbs-size records with newline

lcase change upper case to lower case

ucase change lower case to upper case

sparse try to seek rather than write all-NUL output blocks

swab swap every pair of input bytes

sync pad every input block with NULs to ibs-size; when used with

block or unblock, pad with spaces rather than NULs

excl fail if the output file already exists

nocreat

do not create the output file

notrunc

do not truncate the output file

noerror

continue after read errors

fdatasync

physically write output file data before finishing

fsync likewise, but also write metadata

Each FLAG symbol may be:

append append mode (makes sense only for output; conv=notrunc sug?

gsted)

direct use direct I/O for data

directory

fail unless a directory

dsync use synchronized I/O for data

sync likewise, but also for metadata

fullblock

accumulate full blocks of input (iflag only)

nonblock

use non-blocking I/O

noatime

do not update access time

nocache

Request to drop cache. See also oflag=sync

noctty do not assign controlling terminal from file

nofollow

do not follow symlinks

count\_bytes

treat 'count=N' as a byte count (iflag only)

skip\_bytes

treat 'skip=N' as a byte count (iflag only)

seek\_bytes

treat 'seek=N' as a byte count (oflag only)

Sending a USR1 signal to a running 'dd' process makes it print I/O sta?

tistics to standard error and then resume copying.

Options are:

--help display this help and exit

--version

output version information and exit

## AUTHOR

Written by Paul Rubin, David MacKenzie, and Stuart Kemp.

## REPORTING BUGS

GNU coreutils online help: <<https://www.gnu.org/software/coreutils/>>

Report any translation bugs to <<https://translationproject.org/team/>>

## COPYRIGHT

Copyright ? 2020 Free Software Foundation, Inc. License GPLv3+: GNU

GPL version 3 or later <<https://gnu.org/licenses/gpl.html>>.

This is free software: you are free to change and redistribute it.

There is NO WARRANTY, to the extent permitted by law.

## SEE ALSO

Full documentation <<https://www.gnu.org/software/coreutils/dd>>

or available locally via: info '(coreutils) dd invocation'

GNU coreutils 8.32

January 2023

DD(1)