



Full credit is given to the above companies including the OS that this PDF file was generated!

Rocky Enterprise Linux 9.2 Manual Pages on command 'getpw.3'

\$ man getpw.3

GETPW(3) Linux Programmer's Manual GETPW(3)

NAME

getpw - reconstruct password line entry

SYNOPSIS

```
#define _GNU_SOURCE           /* See feature_test_macros(7) */  
#include <sys/types.h>  
#include <pwd.h>  
  
int getpw(uid_t uid, char *buf);
```

DESCRIPTION

The getpw() function reconstructs the password line entry for the given user ID uid in the buffer buf. The returned buffer contains a line of format

```
name:passwd:uid:gid:gecos:dir:shell
```

The passwd structure is defined in <pwd.h> as follows:

```
struct passwd {  
    char *pw_name;     /* username */  
    char *pw_passwd;   /* user password */  
    uid_t pw_uid;     /* user ID */
```

```

gid_t pw_gid;    /* group ID */
char *pw_gecos; /* user information */
char *pw_dir;   /* home directory */
char *pw_shell; /* shell program */
};

```

For more information about the fields of this structure, see `passwd(5)`.

RETURN VALUE

The `getpw()` function returns 0 on success; on error, it returns -1, and `errno` is set to indicate the error.

If `uid` is not found in the password database, `getpw()` returns -1, sets `errno` to 0, and leaves `buf` unchanged.

ERRORS

0 or `ENOENT`

No user corresponding to `uid`.

`EINVAL` `buf` is `NULL`.

`ENOMEM` Insufficient memory to allocate `passwd` structure.

FILES

`/etc/passwd`

password database file

ATTRIBUTES

For an explanation of the terms used in this section, see `attributes(7)`.

??

?Interface ? Attribute ? Value ?

??

?`getpw()` ? Thread safety ? MT-Safe locale ?

??

CONFORMING TO

SVr2.

BUGS

The `getpw()` function is dangerous as it may overflow the provided `buf` for `buf`. It is obsoleted by `getpwuid(3)`.

SEE ALSO

endpwent(3), fgetpwent(3), getpwent(3), getpwnam(3), getpwuid(3), putp?
went(3), setpwent(3), passwd(5)

COLOPHON

This page is part of release 5.10 of the Linux man-pages project. A description of the project, information about reporting bugs, and the latest version of this page, can be found at <https://www.kernel.org/doc/man-pages/>.

GNU

2017-09-15

GETPW(3)