



Full credit is given to the above companies including the OS that this PDF file was generated!

Rocky Enterprise Linux 9.2 Manual Pages on command 'ipptoolfile.5'

\$ man ipptoolfile.5

ipptoolfile(5) Apple Inc. ipptoolfile(5)

NAME

ipptoolfile - ipptool file format

DESCRIPTION

The ipptool(1) program accepts free-form plain text files that describe one or more IPP requests. Comments start with the "#" character and continue to the end of the line. Each request is enclosed by curly braces, for example:

```
# This is a comment
{
# The name of the test
NAME "Print PDF File"
# The request to send
OPERATION Print-Job
GROUP operation-attributes-tag
ATTR charset attributes-charset utf-8
ATTR language attributes-natural-language en
ATTR uri printer-uri $uri
```

```

ATTR name requesting-user-name $user
ATTR mimeType document-format application/pdf
GROUP job-attributes-tag
ATTR collection media-col {
    # US Letter plain paper from the "main" tray
    MEMBER collection media-size {
        MEMBER integer x-dimension 21590
        MEMBER integer y-dimension 27940
    }
    MEMBER integer media-top-margin 423
    MEMBER integer media-bottom-margin 423
    MEMBER integer media-left-margin 423
    MEMBER integer media-right-margin 423
    MEMBER keyword media-source "main"
    MEMBER keyword media-type "stationery"
}
FILE testfile.pdf
# The response to expect
STATUS successful-ok
EXPECT job-id OF-TYPE integer WITH-VALUE >0
EXPECT job-uri OF-TYPE uri
}
{
    # The name of the test
    NAME "Wait for Job to Complete"
    # The request to send
    OPERATION Get-Job-Attributes
    GROUP operation-attributes-tag
    ATTR charset attributes-charset utf-8
    ATTR language attributes-natural-language en
    ATTR uri printer-uri $uri
    ATTR integer job-id $job-id
    ATTR name requesting-user-name $user

```

```

# The response to expect
STATUS successful-ok
EXPECT job-id OF-TYPE integer WITH-VALUE $job-id
EXPECT job-uri OF-TYPE uri
EXPECT job-state OF-TYPE enum WITH-VALUE >5 REPEAT-NO-MATCH
EXPECT job-originating-user-name OF-TYPE name WITH-VALUE "$user"
# Show the job state until completed...
DISPLAY job-state
DISPLAY job-state-reasons
}

```

TOP-LEVEL DIRECTIVES

The following directives can be used outside of a test:

```
{ test }
```

Defines a test.

```
DEFINE variable-name value
```

Defines the named variable to the given value. This is equivalent to specifying `-d variable-name=value` on the `ipptool(8)` command-line.

```
DEFINE-DEFAULT variable-name value
```

Defines the named variable to the given value if it does not already have a value.

```
FILE-ID "identifier"
```

Specifies an identifier string for the current file.

```
IGNORE-ERRORS yes
```

```
IGNORE-ERRORS no
```

Specifies whether, by default, `ipptool(8)` will ignore errors and continue with subsequent tests.

```
INCLUDE "filename"
```

```
INCLUDE <filename>
```

Includes another test file. The first form includes a file relative to the current test file, while the second form includes a file from the `ipptool(8)` include directory.

```
INCLUDE-IF-DEFINED name "filename"
```

INCLUDE-IF-DEFINED name <filename>

Includes another test file if the named variable is defined. The first form includes a file relative to the current test file, while the second form includes a file from the `ipptool(8)` include directory.

INCLUDE-IF-NOT-DEFINED name "filename"

INCLUDE-IF-NOT-DEFINED name <filename>

Includes another test file if the named variable is not defined. The first form includes a file relative to the current test file, while the second form includes a file from the `ipptool(8)` include directory.

SKIP-IF-DEFINED variable-name

SKIP-IF-NOT-DEFINED variable-name

Specifies that the remainder of the test file should be skipped when the variable is or is not defined.

STOP-AFTER-INCLUDE-ERROR no

STOP-AFTER-INCLUDE-ERROR yes

Specifies whether tests will be stopped after an error in an included file.

TRANSFER auto

Specifies that tests will, by default, use "Transfer-Encoding: chunked" for requests with attached files and "Content-Length:" for requests without attached files.

TRANSFER chunked

Specifies that tests will, by default, use the HTTP/1.1 "Transfer-Encoding: chunked" header. This is the default and is equivalent to specifying `-c` on the `ipptool(8)` command-line. Support for chunked requests is required for conformance with all versions of IPP.

TRANSFER length

Specifies that tests will, by default, use the HTTP/1.0 "Content-Length:" header. This is equivalent to specifying `-l` on the `ipptool(8)` command-line. Support for content length requests is required for conformance with all versions of IPP.

VERSION 1.0

VERSION 1.1

VERSION 2.0

VERSION 2.1

VERSION 2.2

Specifies the default IPP version number to use for the tests that follow.

TEST DIRECTIVES

The following directives are understood within a test:

ATTR out-of-band-tag attribute-name

ATTR tag attribute-name value(s)

Adds an attribute to the test request. Out-of-band tags (admin-define, delete-attribute, no-value, not-settable, unknown, unsupported) have no value. Values for other tags are delimited by the comma (",") character - escape commas using the "\" character. Common attributes and values are listed in the IANA IPP registry - see references below.

ATTR collection attribute-name { MEMBER tag member-name value(s) ... }

[... , { ... }]

Adds a collection attribute to the test request. Member attributes follow the same syntax as regular attributes and can themselves be nested collections. Multiple collection values can be supplied as needed, separated by commas.

COMPRESSION deflate

COMPRESSION gzip

COMPRESSION none

Uses the specified compression on the document data following the attributes in a Print-Job or Send-Document request.

DELAY seconds[,repeat-seconds]

Specifies a delay in seconds before this test will be run. If two values are specified, the second value is used as the delay between repeated tests.

DISPLAY attribute-name

Specifies that value of the named attribute should be output as part of the test report.

EXPECT attribute-name [predicate(s)]

EXPECT ?attribute-name predicate(s)

EXPECT !attribute-name

Specifies that the response must/may/must not include the named attribute. Additional requirements can be added as predicates - see the "EXPECT PREDICATES" section for more information on predicates. Attribute names can specify member attributes by separating the attribute and member names with the forward slash, for example "media-col/media-size/x-dimension".

EXPECT-ALL attribute-name [predicate(s)]

EXPECT-ALL ?attribute-name predicate(s)

Specifies that the response must/may include the named attribute and that all occurrences of that attribute must match the given predicates.

FILE filename

Specifies a file to include at the end of the request. This is typically used when sending a test print file.

GROUP tag

Specifies the group tag for subsequent attributes in the request.

IGNORE-ERRORS yes

IGNORE-ERRORS no

Specifies whether ipptool(8) will ignore errors and continue with subsequent tests.

NAME "literal string"

Specifies the human-readable name of the test.

OPERATION operation-code

Specifies the operation to be performed.

PAUSE "message"

Displays the provided message and waits for the user to press a key to continue.

REQUEST-ID number

REQUEST-ID random

Specifies the request-id value to use in the request, either an integer or the word "random" to use a randomly generated value (the default).

RESOURCE path

Specifies an alternate resource path that is used for the HTTP POST request. The default is the resource from the URI provided to the ipptool(8) program.

SKIP-IF-DEFINED variable-name

SKIP-IF-NOT-DEFINED variable-name

Specifies that the current test should be skipped when the variable is or is not defined.

SKIP-PREVIOUS-ERROR yes

SKIP-PREVIOUS-ERROR no

Specifies whether ipptool(8) will skip the current test if the previous test resulted in an error/failure.

STATUS status-code [predicate]

Specifies an expected response status-code value. Additional requirements can be added as predicates - see the "STATUS PREDICATES" section for more information on predicates.

TEST-ID "identifier"

Specifies an identifier string for the current test.

TRANSFER auto

Specifies that this test will use "Transfer-Encoding: chunked" if it has an attached file or "Content-Length:" otherwise.

TRANSFER chunked

Specifies that this test will use the HTTP/1.1 "Transfer-Encoding: chunked" header.

TRANSFER length

Specifies that this test will use the HTTP/1.0 "Content-Length:" header.

VERSION 1.0

VERSION 1.1

VERSION 2.0

VERSION 2.1

VERSION 2.2

Specifies the IPP version number to use for this test.

EXPECT PREDICATES

The following predicates are understood following the EXPECT test directive:

COUNT number

Requires the EXPECT attribute to have the specified number of values.

DEFINE-MATCH variable-name

Defines the variable to "1" when the EXPECT condition matches. A side-effect of this predicate is that this EXPECT will never fail a test.

DEFINE-NO-MATCH variable-name

Defines the variable to "1" when the EXPECT condition does not match. A side-effect of this predicate is that this EXPECT will never fail a test.

DEFINE-VALUE variable-name

Defines the variable to the value of the attribute when the EXPECT condition matches. A side-effect of this predicate is that this EXPECT will never fail a test.

IF-DEFINED variable-name

Makes the EXPECT conditions apply only if the specified variable is defined.

IF-NOT-DEFINED variable-name

Makes the EXPECT conditions apply only if the specified variable is not defined.

IN-GROUP tag

Requires the EXPECT attribute to be in the specified group tag.

OF-TYPE tag[[tag,...]

Requires the EXPECT attribute to use one of the specified value tag(s).

REPEAT-LIMIT number

Specifies the maximum number of times to repeat if the REPEAT-MATCH or REPEAT-NO-MATCH predicate is specified. The default value is 1000.

REPEAT-MATCH

REPEAT-NO-MATCH

Specifies that the current test should be repeated when the EXPECT condition matches or does not match.

SAME-COUNT-AS attribute-name

Requires the EXPECT attribute to have the same number of values as the specified parallel attribute.

WITH-ALL-HOSTNAMES "literal string"

WITH-ALL-HOSTNAMES "/regular expression/"

Requires that all URI values contain a matching hostname.

WITH-ALL-RESOURCES "literal string"

WITH-ALL-RESOURCES "/regular expression/"

Requires that all URI values contain a matching resource (including leading /).

WITH-ALL-SCHEMES "literal string"

WITH-ALL-SCHEMES "/regular expression/"

Requires that all URI values contain a matching scheme.

WITH-ALL-VALUES "literal string"

Requires that all values of the EXPECT attribute match the literal string. Comparisons are case-sensitive.

WITH-ALL-VALUES <number

WITH-ALL-VALUES =number

WITH-ALL-VALUES >number

WITH-ALL-VALUES number[,...,number]

Requires that all values of the EXPECT attribute match the number(s) or numeric comparison. When comparing rangeOfInteger values, the "<" and ">" operators only check the upper bound of the range.

WITH-ALL-VALUES "false"

WITH-ALL-VALUES "true"

Requires that all values of the EXPECT attribute match the boolean value given.

WITH-ALL-VALUES "/regular expression/"

Requires that all values of the EXPECT attribute match the regular expression, which must conform to the POSIX regular expression syntax. Comparisons are case-sensitive.

WITH-HOSTNAME "literal string"

WITH-HOSTNAME "/regular expression/"

Requires that at least one URI value contains a matching hostname.

WITH-RESOURCE "literal string"

WITH-RESOURCE "/regular expression/"

Requires that at least one URI value contains a matching resource (including leading /).

WITH-SCHEME "literal string"

WITH-SCHEME "/regular expression/"

Requires that at least one URI value contains a matching scheme.

WITH-VALUE "literal string"

Requires that at least one value of the EXPECT attribute matches the literal string. Comparisons are case-sensitive.

WITH-VALUE <number

WITH-VALUE =number

WITH-VALUE >number

WITH-VALUE number[,...,number]

Requires that at least one value of the EXPECT attribute matches the number(s) or numeric comparison. When comparing rangeOfInteger values, the "<" and ">" operators only check the upper bound of the range.

WITH-VALUE "false"

WITH-VALUE "true"

Requires that at least one value of the EXPECT attribute matches the boolean value given.

WITH-VALUE "/regular expression/"

Requires that at least one value of the EXPECT attribute matches the regular expression, which must conform to the POSIX regular expression syntax. Comparisons are case-sensitive.

WITH-VALUE-FROM attribute-name

Requires that the value(s) of the EXPECT attribute matches the value(s) in the specified attribute. For example, "EXPECT job-sheets WITH-VALUE-FROM job-sheets-supported" requires that the "job-sheets" value is listed as a value of the "job-sheets-supported" attribute.

STATUS PREDICATES

The following predicates are understood following the STATUS test directive:

DEFINE-MATCH variable-name

Defines the variable to "1" when the STATUS matches. A side-effect of this predicate is that this STATUS will never fail a test.

DEFINE-NO-MATCH variable-name

Defines the variable to "1" when the STATUS does not match. A side-effect of this predicate is that this STATUS will never fail a test.

IF-DEFINED variable-name

Makes the STATUS apply only if the specified variable is defined.

IF-NOT-DEFINED variable-name

Makes the STATUS apply only if the specified variable is not defined.

REPEAT-LIMIT number

Specifies the maximum number of times to repeat. The default value is 1000.

REPEAT-MATCH

REPEAT-NO-MATCH

Specifies that the current test should be repeated when the response status-code matches or does not match the value specified by the STATUS directive.

OPERATION CODES

Operation codes correspond to the hexadecimal numbers (0xHHHH) and names from RFC 8011 and other IPP extension specifications. Here is a complete list of names supported by ipptool(8):

- Activate-Printer
- CUPS-Accept-Jobs
- CUPS-Add-Modify-Class
- CUPS-Add-Modify-Printer
- CUPS-Authenticate-Job
- CUPS-Delete-Class
- CUPS-Delete-Printer
- CUPS-Get-Classes
- CUPS-Get-Default
- CUPS-Get-Devices
- CUPS-Get-Document
- CUPS-Get-PPD
- CUPS-Get-PPDs
- CUPS-Get-Printers
- CUPS-Move-Job
- CUPS-Reject-Jobs
- CUPS-Set-Default
- Cancel-Current-Job
- Cancel-Job
- Cancel-Jobs
- Cancel-My-Jobs
- Cancel-Subscription
- Close-Job
- Create-Job
- Create-Job-Subscriptions
- Create-Printer-Subscriptions
- Deactivate-Printer
- Disable-Printer
- Enable-Printer
- Get-Job-Attributes

Get-Jobs
Get-Notifications
Get-Printer-Attributes
Get-Printer-Support-Files
Get-Printer-Supported-Values
Get-Subscription-Attributes
Get-Subscriptions
Hold-Job
Hold-New-Jobs
Identify-Printer
Pause-Printer
Pause-Printer-After-Current-Job
Print-Job
Print-URI
Promote-Job
Purge-Jobs
Release-Held-New-Jobs
Release-Job
Renew-Subscription
Reprocess-Job
Restart-Job
Restart-Printer
Resubmit-Job
Resume-Job
Resume-Printer
Schedule-Job-After
Send-Document
Send-Hardcopy-Document
Send-Notifications
Send-URI
Set-Job-Attributes
Set-Printer-Attributes
Shutdown-Printer

Startup-Printer

Suspend-Current-Job

Validate-Document

Validate-Job

STATUS CODES

Status codes correspond to the hexadecimal numbers (0xHHHH) and names from RFC 8011 and other IPP extension specifications. Here is a com?

plete list of the names supported by ipptool(8):

client-error-account-authorization-failed

client-error-account-closed

client-error-account-info-needed

client-error-account-limit-reached

client-error-attributes-not-settable

client-error-attributes-or-values-not-supported

client-error-bad-request

client-error-charset-not-supported

client-error-compression-error

client-error-compression-not-supported

client-error-conflicting-attributes

client-error-document-access-error

client-error-document-format-error

client-error-document-format-not-supported

client-error-document-password-error

client-error-document-permission-error

client-error-document-security-error

client-error-document-unprintable-error

client-error-forbidden

client-error-gone

client-error-ignored-all-notifications

client-error-ignored-all-subscriptions

client-error-not-authenticated

client-error-not-authorized

client-error-not-found

client-error-not-possible
client-error-print-support-file-not-found
client-error-request-entity-too-large
client-error-request-value-too-long
client-error-timeout
client-error-too-many-subscriptions
client-error-uri-scheme-not-supported
cups-error-account-authorization-failed
cups-error-account-closed
cups-error-account-info-needed
cups-error-account-limit-reached
cups-see-other
redirection-other-site
server-error-busy
server-error-device-error
server-error-internal-error
server-error-job-canceled
server-error-multiple-document-jobs-not-supported
server-error-not-accepting-jobs
server-error-operation-not-supported
server-error-printer-is-deactivated
server-error-service-unavailable
server-error-temporary-error
server-error-version-not-supported
successful-ok
successful-ok-but-cancel-subscription
successful-ok-conflicting-attributes
successful-ok-events-complete
successful-ok-ignored-notifications
successful-ok-ignored-or-substituted-attributes
successful-ok-ignored-subscriptions
successful-ok-too-many-events

Value and group tags correspond to the names from RFC 8011 and other

IPP extension specifications. Here are the group tags:

document-attributes-tag

event-notification-attributes-tag

job-attributes-tag

operation-attributes-tag

printer-attributes-tag

subscription-attributes-tag

unsupported-attributes-tag

Here are the value tags:

admin-define

boolean

charset

collection

dateTime

default

delete-attribute

enum

integer

keyword

mimeMediaType

nameWithLanguage

nameWithoutLanguage

naturalLanguage

no-value

not-settable

octetString

rangeOfInteger

resolution

textWithLanguage

textWithoutLanguage

unknown

unsupported

uri

uriScheme

VARIABLES

The `ipptool(8)` program maintains a list of variables that can be used in any literal string or attribute value by specifying "\$variable-name". Aside from variables defined using the `-d` option or `DEFINE` directive, the following pre-defined variables are available:

`$$` Inserts a single "\$" character.

`$ENV[name]`

Inserts the value of the named environment variable, or an empty string if the environment variable is not defined.

`$date-current`

Inserts the current date and time using the ISO-8601 format ("yyyy-mm-ddThh:mm:ssZ").

`$date-start`

Inserts the starting date and time using the ISO-8601 format ("yyyy-mm-ddThh:mm:ssZ").

`$filename`

Inserts the filename provided to `ipptool(8)` with the `-f` option.

`$filetype`

Inserts the MIME media type for the filename provided to `ipptool(8)` with the `-f` option.

`$hostname`

Inserts the hostname from the URI provided to `ipptool(8)`.

`$job-id`

Inserts the last "job-id" attribute value returned in a test response or 0 if no "job-id" attribute has been seen.

`$job-uri`

Inserts the last "job-uri" attribute value returned in a test response or an empty string if no "job-uri" attribute has been seen.

`$notify-subscription-id`

Inserts the last "notify-subscription-id" attribute value returned in a test response or 0 if no "notify-subscription-id" attribute

has been seen.

\$port

Inserts the port number from the URI provided to `ippool(8)`.

\$resource

Inserts the resource path from the URI provided to `ippool(8)`.

\$scheme

Inserts the scheme from the URI provided to `ippool(8)`.

\$uri Inserts the URI provided to `ippool(8)`.

\$uriuser

Inserts the username from the URI provided to `ippool(8)`, if any.

\$user

Inserts the current user's login name.

SEE ALSO

`ippool(1)`, IANA IPP Registry (<http://www.iana.org/assignments/ipp-reg?istrations>), PWG Internet Printing Protocol Workgroup (<http://www.pwg.org/ipp>), RFC 8011 (<http://tools.ietf.org/html/rfc8011>)

COPYRIGHT

Copyright ? 2007-2019 by Apple Inc.

15 August 2019

CUPS

`ippoolfile(5)`