

Full credit is given to the above companies including the OS that this PDF file was generated!

Rocky Enterprise Linux 9.2 Manual Pages on command 'p11tool.1'

# \$ man p11tool.1

p11tool(1)

p11tool(1)

# NAME

p11tool - GnuTLS PKCS #11 tool

# SYNOPSIS

p11tool [-flags] [-flag [value]] [--option-name[[=| ]value]] [url]

User Commands

Operands and options may be intermixed. They will be reordered.

# DESCRIPTION

Program that allows operations on PKCS #11 smart cards and security modules.

To use PKCS #11 tokens with GnuTLS the p11-kit configuration files need

to be setup. That is create a .module file in /etc/pkcs11/modules with

the contents 'module: /path/to/pkcs11.so'. Alternatively the configu?

ration file /etc/gnutls/pkcs11.conf has to exist and contain a number

of lines of the form 'load=/usr/lib/opensc-pkcs11.so'.

You can provide the PIN to be used for the PKCS #11 operations with the

environment variables GNUTLS\_PIN and GNUTLS\_SO\_PIN.

# OPTIONS

--list-tokens

List all available tokens.

--list-token-urls

List the URLs available tokens.

This is a more compact version of --list-tokens.

#### --list-mechanisms

List all available mechanisms in a token.

#### --initialize

Initializes a PKCS #11 token.

--initialize-pin

Initializes/Resets a PKCS #11 token user PIN.

#### --initialize-so-pin

Initializes/Resets a PKCS #11 token security officer PIN.

This initializes the security officer's PIN. When used non-in?

teractively use the GNUTLS\_NEW\_SO\_PIN environment variables to

initialize SO's PIN.

#### --set-pin=str

Specify the PIN to use on token operations.

Alternatively the GNUTLS\_PIN environment variable may be used.

#### --set-so-pin=str

Specify the Security Officer's PIN to use on token initializa?

tion.

Alternatively the GNUTLS\_SO\_PIN environment variable may be

used.

### **Object listing**

#### --list-all

List all available objects in a token.

All objects available in the token will be listed. That includes

objects which are potentially unaccessible using this tool.

### --list-all-certs

List all available certificates in a token.

That option will also provide more information on the certifi?

cates, for example, expand the attached extensions in a trust

token (like p11-kit-trust).

### --list-certs

List all certificates that have an associated private key.

That option will only display certificates which have a private

key associated with them (share the same ID).

#### --list-all-privkeys

List all available private keys in a token.

Lists all the private keys in a token that match the specified

URL.

## --list-privkeys

This is an alias for the --list-all-privkeys option.

#### --list-keys

This is an alias for the --list-all-privkeys option.

#### --list-all-trusted

List all available certificates marked as trusted.

#### --export

Export the object specified by the URL. This option must not appear in combination with any of the following options: export-

stapled, export-chain, export-pubkey.

#### --export-stapled

Export the certificate object specified by the URL. This option must not appear in combination with any of the following op? tions: export, export-chain, export-pubkey.

Exports the certificate specified by the URL while including any attached extensions to it. Since attached extensions are a p11-kit extension, this option is only available on p11-kit reg? istered trust modules.

#### --export-chain

Export the certificate specified by the URL and its chain of trust. This option must not appear in combination with any of the following options: export-stapled, export, export-pubkey. Exports the certificate specified by the URL and generates its chain of trust based on the stored certificates in the module. --export-pubkey

Export the public key for a private key. This option must not

appear in combination with any of the following options: export-

stapled, export, export-chain.

Exports the public key for the specified private key

--info List information on an available object in a token.

--trusted

This is an alias for the --mark-trusted option.

--distrusted

This is an alias for the --mark-distrusted option.

#### Key generation

--generate-privkey=str

Generate private-public key pair of given type.

Generates a private-public key pair in the specified token. Ac?

ceptable types are RSA, ECDSA, Ed25519, and DSA. Should be com?

bined with --sec-param or --bits.

#### --generate-rsa

Generate an RSA private-public key pair.

Generates an RSA private-public key pair on the specified token.

Should be combined with --sec-param or --bits.

NOTE: THIS OPTION IS DEPRECATED

--generate-dsa

Generate a DSA private-public key pair.

Generates a DSA private-public key pair on the specified token.

Should be combined with --sec-param or --bits.

NOTE: THIS OPTION IS DEPRECATED

--generate-ecc

Generate an ECDSA private-public key pair.

Generates an ECDSA private-public key pair on the specified to?

ken. Should be combined with --curve, --sec-param or --bits.

NOTE: THIS OPTION IS DEPRECATED

--bits=num

Specify the number of bits for the key generate. This option

takes an integer number as its argument.

For applications which have no key-size restrictions the

--sec-param option is recommended, as the sec-param levels will

adapt to the acceptable security levels with the new versions of

gnutls.

#### --curve=str

Specify the curve used for EC key generation.

Supported values are secp192r1, secp224r1, secp256r1, secp384r1

and secp521r1.

--sec-param=security parameter

Specify the security level.

This is alternative to the bits option. Available options are

[low, legacy, medium, high, ultra].

## Writing objects

# --set-id=str

Set the CKA\_ID (in hex) for the specified by the URL object.

This option must not appear in combination with any of the fol?

lowing options: write.

Modifies or sets the CKA\_ID in the specified by the URL object.

The ID should be specified in hexadecimal format without a '0x' prefix.

#### --set-label=str

Set the CKA\_LABEL for the specified by the URL object. This op? tion must not appear in combination with any of the following

options: write, set-id.

Modifies or sets the CKA\_LABEL in the specified by the URL ob?

# ject

#### --write

Writes the loaded objects to a PKCS #11 token. It can be used to write private, public keys, certificates or secret keys to a token. Must be combined with one of --load-privkey, --load-pubkey, --load-certificate option. When writing a certificate object, its CKA\_ID is set to the same CKA\_ID of the corresponding public key, if it exists on the to?

ken; otherwise it will be derived from the X.509 Subject Key

Identifier of the certificate. If this behavior is undesired,

write the public key to the token beforehand.

#### --delete

Deletes the objects matching the given PKCS #11 URL.

### --label=str

Sets a label for the write operation.

#### --id=str

Sets an ID for the write operation.

Sets the CKA\_ID to be set by the write operation. The ID should

be specified in hexadecimal format without a '0x' prefix.

--mark-wrap, --no-mark-wrap

Marks the generated key to be a wrapping key. The no-mark-wrap

form will disable the option.

Marks the generated key with the CKA\_WRAP flag.

### --mark-trusted, --no-mark-trusted

Marks the object to be written as trusted. This option must not

appear in combination with any of the following options: mark-

distrusted. The no-mark-trusted form will disable the option.

Marks the object to be generated/written with the CKA\_TRUST

flag.

--mark-distrusted

When retrieving objects, it requires the objects to be dis?

trusted (blacklisted). This option must not appear in combina?

tion with any of the following options: mark-trusted.

Ensures that the objects retrieved have the CKA\_X\_TRUST flag.

This is p11-kit trust module extension, thus this flag is only

valid with p11-kit registered trust modules.

### --mark-decrypt, --no-mark-decrypt

Marks the object to be written for decryption. The no-mark-de?

crypt form will disable the option.

Marks the object to be generated/written with the CKA\_DECRYPT

flag set to true.

--mark-sign, --no-mark-sign

Marks the object to be written for signature generation. The

no-mark-sign form will disable the option.

Marks the object to be generated/written with the CKA\_SIGN flag

set to true.

--mark-ca, --no-mark-ca

Marks the object to be written as a CA. The no-mark-ca form

will disable the option.

Marks the object to be generated/written with the CKA\_CERTIFI?

CATE\_CATEGORY as CA.

--mark-private, --no-mark-private

Marks the object to be written as private. The no-mark-private

form will disable the option.

Marks the object to be generated/written with the CKA\_PRIVATE

flag. The written object will require a PIN to be used.

--ca This is an alias for the --mark-ca option.

--private

This is an alias for the --mark-private option.

--mark-always-authenticate, --no-mark-always-authenticate

Marks the object to be written as always authenticate. The

no-mark-always-authenticate form will disable the option.

Marks the object to be generated/written with the CKA\_ALWAYS\_AU?

THENTICATE flag. The written object will Mark the object as re?

quiring authentication (pin entry) before every operation.

--secret-key=str

Provide a hex encoded secret key.

This secret key will be written to the module if --write is

specified.

--load-privkey=file

Private key file to use.

--load-pubkey=file

Public key file to use.

--load-certificate=file

Certificate file to use.

### Other options

-d num, --debug=num

Enable debugging. This option takes an integer number as its

argument. The value of num is constrained to being:

in the range 0 through 9999

Specifies the debug level.

## --outfile=str

Output file.

### --login, --no-login

Force (user) login to token. The no-login form will disable the

option.

### --so-login, --no-so-login

Force security officer login to token. The no-so-login form

will disable the option.

Forces login to the token as security officer (admin).

#### --admin-login

This is an alias for the --so-login option.

#### --test-sign

Tests the signature operation of the provided object.

It can be used to test the correct operation of the signature

operation. If both a private and a public key are available

this operation will sign and verify the signed data.

### --sign-params=str

Sign with a specific signature algorithm.

This option can be combined with --test-sign, to sign with a

specific signature algorithm variant. The only option supported

is 'RSA-PSS', and should be specified in order to use RSA-PSS

signature on RSA keys.

### --hash=str

Hash algorithm to use for signing.

This option can be combined with test-sign. Available hash func?

tions are SHA1, RMD160, SHA256, SHA384, SHA512, SHA3-224,

SHA3-256, SHA3-384, SHA3-512.

--generate-random=num

Generate random data. This option takes an integer number as

its argument.

Asks the token to generate a number of bytes of random bytes.

### -8, --pkcs8

Use PKCS #8 format for private keys.

--inder, --no-inder

Use DER/RAW format for input. The no-inder form will disable

the option.

Use DER/RAW format for input certificates and private keys.

### --inraw

This is an alias for the --inder option.

### --outder, --no-outder

Use DER format for output certificates, private keys, and DH pa?

rameters. The no-outder form will disable the option.

The output will be in DER or RAW format.

#### --outraw

This is an alias for the --outder option.

## --provider=file

Specify the PKCS #11 provider library.

This will override the default options in

/etc/gnutls/pkcs11.conf

### --provider-opts=str

Specify parameters for the PKCS #11 provider library.

This is a PKCS#11 internal option used by few modules.

Mainly for testing PKCS#11 modules.

## NOTE: THIS OPTION IS DEPRECATED

## --detailed-url, --no-detailed-url

Print detailed URLs. The no-detailed-url form will disable the

option.

Print a compact listing using only the URLs.

#### --batch

Disable all interaction with the tool.

In batch mode there will be no prompts, all parameters need to

be specified on command line.

### -v arg, --version=arg

Output version of program and exit. The default mode is `v', a

simple version. The `c' mode will print copyright information

and `n' will print the full copyright notice.

-h, --help

Display usage information and exit.

-!, --more-help

Pass the extended usage information through a pager.

## EXAMPLES

To view all tokens in your system use:

\$ p11tool --list-tokens

To view all objects in a token use:

\$ p11tool --login --list-all "pkcs11:TOKEN-URL"

To store a private key and a certificate in a token run:

\$ p11tool --login --write "pkcs11:URL" --load-privkey key.pem --label "Mykey"

\$ p11tool --login --write "pkcs11:URL" --load-certificate cert.pem --label "Mykey"

Note that some tokens require the same label to be used for the cer?

tificate and its corresponding private key.

To generate an RSA private key inside the token use:

\$ p11tool --login --generate-privkey rsa --bits 1024 --label "MyNewKey" --outfile MyNewKey.pub

## "pkcs11:TOKEN-URL"

The bits parameter in the above example is explicitly set because some

tokens only support limited choices in the bit length. The output file

is the corresponding public key. This key can be used to general a cer?

tificate request with certtool.

certtool --generate-request --load-privkey "pkcs11:KEY-URL" --load-pubkey MyNewKey.pub --outfile request.pem

## EXIT STATUS

One of the following exit values will be returned:

# 0 (EXIT\_SUCCESS)

Successful program execution.

1 (EXIT\_FAILURE)

The operation failed or the command syntax was not valid.

# SEE ALSO

certtool (1)

# AUTHORS

# COPYRIGHT

Copyright (C) 2020-2021 Free Software Foundation, and others all rights

reserved. This program is released under the terms of the GNU General

Public License, version 3 or later

# BUGS

Please send bug reports to: bugs@gnutls.org

3.7.6 27 May 2022 p11tool(1)