Rocky Enterprise Linux 9.2 Manual Pages on command 'pthread_create.3'

$ man pthread_create.3

PTHREAD_CREATE(3) Linux Programmer's Manual PTHREAD_CREATE(3)

NAME

pthread_create - create a new thread

SYNOPSIS

#include <pthread.h>

int pthread_create(pthread_t *thread, const pthread_attr_t *attr,

void *(*start_routine) (void *), void *arg);

Compile and link with -pthread.

DESCRIPTION

The pthread_create() function starts a new thread in the calling process. The new thread starts execution by invoking start_routine(); arg is passed as the sole argument of start_routine().

The new thread terminates in one of the following ways:

* It calls pthread_exit(3), specifying an exit status value that is available to another thread in the same process that calls pthread_join(3).

* It returns from start_routine(). This is equivalent to calling pthread_exit(3) with the value supplied in the return statement.

* It is canceled (see pthread_cancel(3)).

* Any of the threads in the process calls exit(3), or the main thread performs a return from main(). This causes the termination of all threads in the process.

The attr argument points to a pthread_attr_t structure whose contents are used at thread creation time to determine attributes for the new thread; this structure is initialized using pthread_attr_init(3) and related functions. If attr is NULL, then the thread is created with default attributes.

Before returning, a successful call to pthread_create() stores the ID of the new thread in the buffer pointed to by thread; this identifier is used to refer to the thread in subsequent calls to other pthreads functions.

The new thread inherits a copy of the creating thread's signal mask (pthread_sigmask(3)). The set of pending signals for the new thread is empty (sigpending(2)). The new thread does not inherit the creating thread's alternate signal stack (sigaltstack(2)).

The new thread inherits the calling thread's floating-point environment (fenv(3)).

The initial value of the new thread's CPU-time clock is 0 (see pthread_getcpuclockid(3)).

Linux-specific details

The new thread inherits copies of the calling thread's capability sets (see capabilities(7)) and CPU affinity mask (see sched_setaffinity(2)).

RETURN VALUE

On success, pthread_create() returns 0; on error, it returns an error number, and the contents of *thread are undefined.

ERRORS

EAGAIN Insufficient resources to create another thread.

EAGAIN A system-imposed limit on the number of threads was encountered.

There are a number of limits that may trigger this error: the RLIMIT_NPROC soft resource limit (set via setrlimit(2)), which limits the number of processes and threads for a real user ID,

was reached; the kernel's system-wide limit on the number of processes and threads, /proc/sys/kernel/threads-max, was reached (see proc(5)); or the maximum number of PIDs, /proc/sys/ker? nel/pid_max, was reached (see proc(5)).

EINVAL Invalid settings in attr.

EPERM No permission to set the scheduling policy and parameters speci? fied in attr.

ATTRIBUTES

For an explanation of the terms used in this section, see at? tributes(7).

Interface	Attribute	Value
pthread_create()	Thread safety	MT-Safe

CONFORMING TO

POSIX.1-2001, POSIX.1-2008.

NOTES

See pthread_self(3) for further information on the thread ID returned in *thread by pthread_create(). Unless real-time scheduling policies are being employed, after a call to pthread_create(), it is indetermi? nate which thread?the caller or the new thread?will next execute.

A thread may either be joinable or detached. If a thread is joinable, then another thread can call pthread_join(3) to wait for the thread to terminate and fetch its exit status. Only when a terminated joinable thread has been joined are the last of its resources released back to the system. When a detached thread terminates, its resources are auto? matically released back to the system: it is not possible to join with the thread in order to obtain its exit status. Making a thread de? tached is useful for some types of daemon threads whose exit status the application does not need to care about. By default, a new thread is created in a joinable state, unless attr was set to create the thread in a detached state (using pthread_attr_setdetachstate(3)).

Under the NPTL threading implementation, if the RLIMIT_STACK soft re?
source limit at the time the program started has any value other than
"unlimited", then it determines the default stack size of new threads.
Using pthread_attr_setstacksize(3), the stack size attribute can be ex?
plicitly set in the attr argument used to create a thread, in order to
obtain a stack size other than the default. If the RLIMIT_STACK re?
source limit is set to "unlimited", a per-architecture value is used
for the stack size. Here is the value for a few architectures:

Architecture	Default stack size
i386	2 MB
IA-64	32 MB
PowerPC	4 MB
S/390	2 MB
Sparc-32	2 MB
Sparc-64	4 MB
x86_64	2 MB

BUGS

In the obsolete LinuxThreads implementation, each of the threads in a
process has a different process ID. This is in violation of the POSIX
threads specification, and is the source of many other nonconformances
to the standard; see pthreads(7).

EXAMPLES

The program below demonstrates the use of pthread_create(), as well as
a number of other functions in the pthreads API.

In the following run, on a system providing the NPTL threading imple?
mentation, the stack size defaults to the value given by the "stack
size" resource limit:

```
$ ulimit -s
8192            # The stack size limit is 8 MB (0x800000 bytes)
$ ./a.out hola salut servus
Thread 1: top of stack near 0xb7dd03b8; argv_string=hola
Thread 2: top of stack near 0xb75cf3b8; argv_string=salut
Thread 3: top of stack near 0xb6dce3b8; argv_string=servus
Joined with thread 1; returned value was HOLA
Joined with thread 2; returned value was SALUT
Joined with thread 3; returned value was SERVUS
```

In the next run, the program explicitly sets a stack size of 1 MB (us?
ing pthread_attr_setstacksize(3)) for the created threads:

```
$ ./a.out -s 0x100000 hola salut servus
Thread 1: top of stack near 0xb7d723b8; argv_string=hola
Thread 2: top of stack near 0xb7c713b8; argv_string=salut
Thread 3: top of stack near 0xb7b703b8; argv_string=servus
Joined with thread 1; returned value was HOLA
Joined with thread 2; returned value was SALUT
Joined with thread 3; returned value was SERVUS
```

Program source

```
#include <pthread.h>
#include <string.h>
#include <stdio.h>
#include <stdlib.h>
#include <unistd.h>
#include <errno.h>
#include <ctype.h>
#define handle_error_en(en, msg) \
        do { errno = en; perror(msg); exit(EXIT_FAILURE); } while (0)
#define handle_error(msg) \
        do { perror(msg); exit(EXIT_FAILURE); } while (0)
```

```
struct thread_info {    /* Used as argument to thread_start() */
    pthread_t thread_id;        /* ID returned by pthread_create() */
    int       thread_num;       /* Application-defined thread # */
    char     *argv_string;      /* From command-line argument */
};
/* Thread start function: display address near top of our stack,
   and return upper-cased copy of argv_string */
static void *
thread_start(void *arg)
{
    struct thread_info *tinfo = arg;
    char *uargv;
    printf("Thread %d: top of stack near %p; argv_string=%s\n",
            tinfo->thread_num, &p, tinfo->argv_string);
    uargv = strdup(tinfo->argv_string);
    if (uargv == NULL)
        handle_error("strdup");
    for (char *p = uargv; *p != '\0'; p++)
        *p = toupper(*p);
    return uargv;
}
int
main(int argc, char *argv[])
{
    int s, opt, num_threads;
    pthread_attr_t attr;
    size_t stack_size;
    void *res;
    /* The "-s" option specifies a stack size for our threads */
    stack_size = -1;
    while ((opt = getopt(argc, argv, "s:")) != -1) {
        switch (opt) {
        case 's':
```

```
            stack_size = strtoul(optarg, NULL, 0);
            break;
        default:
            fprintf(stderr, "Usage: %s [-s stack-size] arg...\n",
                    argv[0]);
            exit(EXIT_FAILURE);
        }
    }
    num_threads = argc - optind;
    /* Initialize thread creation attributes */
    s = pthread_attr_init(&attr);
    if (s != 0)
        handle_error_en(s, "pthread_attr_init");
    if (stack_size > 0) {
        s = pthread_attr_setstacksize(&attr, stack_size);
        if (s != 0)
            handle_error_en(s, "pthread_attr_setstacksize");
    }
    /* Allocate memory for pthread_create() arguments */
    struct thread_info *tinfo = calloc(num_threads, sizeof(*tinfo));
    if (tinfo == NULL)
        handle_error("calloc");
    /* Create one thread for each command-line argument */
    for (int tnum = 0; tnum < num_threads; tnum++) {
        tinfo[tnum].thread_num = tnum + 1;
        tinfo[tnum].argv_string = argv[optind + tnum];
        /* The pthread_create() call stores the thread ID into
           corresponding element of tinfo[] */
        s = pthread_create(&tinfo[tnum].thread_id, &attr,
                           &thread_start, &tinfo[tnum]);
        if (s != 0)
            handle_error_en(s, "pthread_create");
    }
```

```
        /* Destroy the thread attributes object, since it is no
           longer needed */

        s = pthread_attr_destroy(&attr);
        if (s != 0)
            handle_error_en(s, "pthread_attr_destroy");

        /* Now join with each thread, and display its returned value */

        for (int tnum = 0; tnum < num_threads; tnum++) {
            s = pthread_join(tinfo[tnum].thread_id, &res);
            if (s != 0)
                handle_error_en(s, "pthread_join");

            printf("Joined with thread %d; returned value was %s\n",
                    tinfo[tnum].thread_num, (char *) res);
            free(res);      /* Free memory allocated by thread */
        }

        free(tinfo);
        exit(EXIT_SUCCESS);
    }
```

SEE ALSO

getrlimit(2), pthread_attr_init(3), pthread_cancel(3), pthread_detach(3), pthread_equal(3), pthread_exit(3), pthread_getattr_np(3), pthread_join(3), pthread_self(3), pthread_setattr_default_np(3), pthreads(7)

COLOPHON

This page is part of release 5.10 of the Linux man-pages project. A description of the project, information about reporting bugs, and the latest version of this page, can be found at https://www.kernel.org/doc/man-pages/.