#### **NAME**

ldexp, ldexpf, ldexpl – multiply floating-point number by integral power of 2

## **SYNOPSIS**

```
#include <math.h>
```

```
double ldexp(double x, int exp);
float ldexpf(float x, int exp);
long double ldexpl(long double x int ex
```

long double ldexpl(long double x, int exp);

Link with -lm.

Feature Test Macro Requirements for glibc (see **feature\_test\_macros**(7)):

```
ldexpf(), ldexpl():
```

```
_ISOC99_SOURCE || _POSIX_C_SOURCE >= 200112L || /* Since glibc 2.19: */ _DEFAULT_SOURCE || _SVID_SOURCE || _SVID_SOURCE
```

#### DESCRIPTION

These functions return the result of multiplying the floating-point number x by 2 raised to the power exp.

#### **RETURN VALUE**

On success, these functions return  $x * (2^exp)$ .

If exp is zero, then x is returned.

If x is a NaN, a NaN is returned.

If x is positive infinity (negative infinity), positive infinity (negative infinity) is returned.

If the result underflows, a range error occurs, and zero is returned.

If the result overflows, a range error occurs, and the functions return **HUGE\_VAL**, **HUGE\_VALF**, or **HUGE VALL**, respectively, with a sign the same as x.

#### **ERRORS**

See **math\_error**(7) for information on how to determine whether an error has occurred when calling these functions.

The following errors can occur:

Range error, overflow

errno is set to ERANGE. An overflow floating-point exception (FE OVERFLOW) is raised.

Range error, underflow

errno is set to ERANGE. An underflow floating-point exception (FE\_UNDERFLOW) is raised.

# **ATTRIBUTES**

For an explanation of the terms used in this section, see **attributes**(7).

Interface	Attribute	Value
ldexp(),ldexpf(),ldexpl()	Thread safety	MT-Safe

### **CONFORMING TO**

C99, POSIX.1-2001, POSIX.1-2008.

The variant returning *double* also conforms to SVr4, 4.3BSD, C89.

## **SEE ALSO**

```
frexp(3), modf(3), scalbln(3)
```

## **COLOPHON**

This page is part of release 5.05 of the Linux *man-pages* project. A description of the project, information about reporting bugs, and the latest version of this page, can be found at https://www.kernel.org/doc/man-pages/.

2017-09-15